SEND it

MANUAL

INTRODUCTION

SEND-IT is a plug-in for Pro Tools users who need advanced control over their sends. It offers a number of possibilities like PrePost automation, track specific trim modes or complex send links.

Visualize each track's sends in a simple mixer and adjust send levels, trim, pan, PrePost fader states, mute, LFE, block... SEND-IT can automatically update its interface depending on your track selection.

SEND-IT also lets you create, delete, rename, move and color-code your sends across multiple tracks and slots at once.

Need to manage sends across an entire session? Switch to Matrix mode to get a clear overview of all your send assignments and settings. Select any sends and adjust their parameters simultaneously, making even complex sessions easier to navigate.

MINIMUM SYSTEM REQUIREMENTS

- macOS 13.0 or higher (Intel / Apple Silicon) (64-bit).
- iLok 2 or higher (dongle, computer or cloud protection).
- Pro Tools 2024.10 or higher.

HAL AUDIO

Based in Paris (France), at the heart of POLYSON creative campus, HAL Audio is a team of sound engineers, sound editors, re-recording mixers and developers.

Our team has been supporting directors and composers for more than 20 years, dedicated to implementing the sound of their artistic creations. From international blockbusters to indie movies, podcasts, installation art and more, our work can be heard on hundreds of projects.

HAL Audio seeks to develop innovative tools that are created by and destined for post-production professionals, focusing on innovation, audio quality and simplicity of use.

If you have any questions or feedback, feel free to email us at **help@hal-audio.com**.

KEY FEATURES

1 EVERY SEND IN ONE PLACE

View and manipulate all your track sends from an intuitive mixer-style interface.

2 PRE/POST AUTOMATION

Automate each send's pre/post fader state, a parameter Pro Tools doesn't normally allow you to automate.

3 MATRIX VIEW

Manage sends across your entire session. Link any send, from any track and edit their parameters simultaneously.

4 ULTIMATE SENDS MANAGER

Create, delete, rename, move and color-code multiple sends at once in the same window.

HOW TO INSTALL

1 RUN THE INSTALLER

The SEND-IT installer can be downloaded from the product page right here: https://www.hal-audio.com/downloads/#send-it

After downloading and opening the SEND-IT installer, please follow the on-screen instructions. Files will be copied into the right folders. Restart Pro Tools if it was running during the installation. The engine the plug-in automatically when next relaunching and you will be asked to register Boom-it with your iLok account.

2 ILOK REGISTRATION

SEND-IT is licensed using the iLok system and you need to have an iLok account in order to use it. Note that setting up an iLok account is free and you will find all necessary information on how to do it on www.ilok.com

After your purchase, you will automatically receive an order confirmation from us containing an iLok activation code in the following format: XXXX-XXXX-XXXX-XXXX-XXXX-XXXX-XXXX-XX

To activate your license:

1. Download and open the iLok License Manager application (available for free at www.ilok.com)
2. From the menu bar, select Licenses > Redeem Activation Code, or click the Redeem Activation Code icon in the upper-right corner of the window.
3. Copy and paste the full activation code into the entry field.
4. Choose your preferred activation location: iLok USB dongle, iLok Cloud, or your local computer.
5. Confirm to complete the activation.

If you activate SEND-IT on an iLok USB dongle, the dongle containing the active license must be connected to your computer whenever you use the plug-in.

3 QUICK START

SEND-IT is an AAX plug-in. It displays and controls all Pro Tools sends in a single window, and makes their Pre/Post automatable. Control Pro Tools like never before.

HOW TO USE

SENDS PAGE 1/2



1 PAGE SWITCH

Navigate from the SENDS page to the MATRIX page

2 TRACK MENU

Choose the Pro Tools track with a SEND-IT instance for which you want to control the sends.

3 FOLLOW TRACK SELECTION

When this button is active, the SEND-IT display follows the track selections made Pro Tools.

4 UNDO / REDO

Reverses or reapplies the most recent action.

5 INFO & SIZE

- ⓘ Displays an interactive manual.
- ⤢ Chooses the interface size and the amount of sends to display in (1 or 12).

SENDS PAGE 2/2



1 ROUTING MENU

Select the desired signal path destination.

2 PRE / POST

Choose whether the signal path is tapped before or after the track's volume fader. With SEND-IT, PrePost is now automatable.

Please note that PrePost automation is not considered in bounces. To print them record the bus in real time.

3 FOLLOW MAIN PAN

Links the track's send panner directly to its main channel panner.

4 PAN

Set the desired pan position.

5 MUTE

Mute an individual send.

6 TRIM / LFE

Choose whether you want the track fader to control the VOLUME, the VOLUME TRIM or the LFE SEND level.

MATRIX PAGE

1 SEARCH BAR

Filter the table view to show only tracks with the search terms.

2 TRACK TYPE

Filter the table view to show only a specific track type (All / Audio / Aux / Folder / Instrument).

3 MATRIX DISPLAY

Click on one of the button slide to update the matrix display:

- VOL : Shows the volume level of each send.
- PAN : Shows the pan position of each send.
- TRIM : Shows the pre position of each send.
- MUTE : Indicates the mute state of each send.
- PRE / POST : displays whether each send's pre-fader or post-fader.
- LFE : Shows the LFE send level of each send.



CREDITS

CONCEPTION
Loïc Dewisme
Cyril Holtz
Antoine Martin
Lucien Richardson

ENGINEERING
Loïc Dewisme

GRAPHIC DESIGN
Loïc Dewisme
Antoine Martin
Benjamin Remise

MARKETING
Clément Friedrich
Lucie Dewisme
Loïc Dewisme

USER MANUAL
Soriya Moreaud
Benjamin Remise

WEBSITE
Benjamin Remise
Vincent Zanetto

BETA TESTING
Florent Lavallée
Thibaud Loyer

ADMINISTRATION
Charles Bussiere
Nicolas Naegelen
Laëtitia Nuber
Ana Vallejo

THANKS
Thibaud Naine
Rodrigo Serio
Tom Mauvoy

©2024 HAL. All rights reserved.